

Operation

- [Useful CLI Commands Univention Corporate Server](#)

Useful CLI Commands

Univention Corporate Server

Useful CLI command line troubleshooting tools

The following is a list of CLI commands used for administering the Univention Corporate Server (UCS)

UCS Show Commands

Command	Description
ucr get server/role	Show the server role
ucr get domainname	Show Domainname
ucr get windows/domain	Show WIndows Domain

UCS Edit Commands

Command	Description
/usr/share/univention-samba4/scripts/purge_s4_computer.py --computername=backupdomaincontroller	Uninstallation of Backup Domain Controller, see here: https://docs.software-univention.de/ext-windows/latest/en/#ext-win-s4-deinstall

Samba Show Commands

For Samba 4 Troubleshooting check this article: <https://help.univention.com/t/samba-4-troubleshooting/32>

Command	Description
samba-tool drs showrepl	To get an overview of the current drs replication status you can use this command at every UCS Samba 4 DC which is joined to the domain.

Command	Description
root@master:~# univention-s4search cn=master msDS-KeyVersionNumber root@backup:~# univention-s4search cn=master msDS-KeyVersionNumber	<p>For a given user, computer, or built-in account, this attribute specifies the Kerberos version number of the current key for that account. Therefore it can be used to compare the replication status of systems.</p> <p>The values have to be equal - otherwise the replication seems to be broken. If a system uses another value in comparison to the master, then it has to be rejoined or you first try to replicate just the Server account.</p> <p>Example:</p> <pre> root@master:~# univention-s4search cn=master msDS- KeyVersionNumber dn: CN=MASTER,OU=Domain Controllers,DC=test,DC=domain msDS-KeyVersionNumber: 7 root@backup:~# univention-s4search cn=master msDS- KeyVersionNumber dn: CN=MASTER,OU=Domain Controllers,DC=test,DC=domain msDS-KeyVersionNumber: 1 </pre>
samba-tool dbcheck --cross-ncs	<p>This checks the database of samba4. Samba saves its data not just in one database, but it splits it up in 5 partitions. To check all partitions and not just the basic one you need to add the parameter <code>--cross-ncs</code></p>
samba-tool dbcheck --cross-ncs --fix --yes	To fix upcoming issues you can use <code>--fix</code> and <code>--yes</code> if you do not want to be asked for approval each error or warning.
/usr/share/univention-samba4/scripts/check_essential_samba4_dns_records.sh	For a complete overview of the relevant dns records.